



**INSTALLATION
AND
REGISTRATION
MANUAL**



www.abraxasenergy.com

Installing Metrix 4.4

- 1. IMPORTANT: Before any software installation, make back up copies of your work!** Abraxas Energy assumes no responsibility for any loss or damage to files during installation.
- 2. Do you know your Max Release Data?** Free upgrades are included for 1 year from the date of the initial Metrix purchase. This date is coded into a License it cannot unlock version of Metrix that are released after this date. If it has been longer than a year OR you are unsure of your Max Release Date, contact us through our request page:

<http://www.abraxasenergy.com/energytoolbox/lic/index.php>

3. Installations

- a) Close any windows of Excel or Metrix currently running.**
- b) Uninstall any pre existing version of Metrix 4.0 or higher.** This ensures the current version is in use, and helps to prevent any unintentional duplicate installations.
- c) Go to our Official Metrix Release Page:**


[http://www.abraxasenergy.com/energytoolbox/official_metrix_releases.p
hp](http://www.abraxasenergy.com/energytoolbox/official_metrix_releases.php)

Select the version of Metrix you are current for. (see Max Release Date)

d) Save the setup file to your computer (not a network drive) where you can find it. (Desktop is generally best). After installation, the setup file may be deleted.



e) Double click the Setup File Icon (shown below) to start the install process. Follow the on-screen prompts to select installation options.



f) NOTE: default installation settings are highly recommended.

4. Excel 2003 Settings

a) NOTE: if prompted, macros must be enabled when opening Report Maker.

b) With Excel open, go to: Tools > Macro > Security.

- c) On the 1st tab of the box that pops up, set macro security to medium. This settings allows users to choose if they want to allow macros on every instance they are used.



- d) Next, go to the 2nd tab for trusted publishers. Make sure both boxes are checked for installed add-ins / templates and access to visual basic project.

5. Excel 2007 Settings

- a) **NOTE: if prompted, macros must be enabled when opening Report Maker.**
- b) With Excel open, go to the Microsoft logo in the upper



- c) Bubble in “Disable all macros except digitally signed macros”.
- d) Check the box to “Trust access to VBA project object model”.

6. Licensing Quick Facts


- a) **A Full License must be re-imported when:** installing a new version of Metrix OR transferring to a new computer.
- b) **Only one License is needed for both Metrix and Report Maker.** Fastdata Deluxe and associated Routines must be purchased separately.
- c) **A License must match 2 things:** Computer ID and Max Release Date.
- d) **Computer ID:** This is like a fingerprint for your computer. One license will work for only one Computer ID and therefore only one computer. Computer ID is displayed in the License Importer and the Status Box.
- e) **License Status Box:** Displays Computer ID, Expiration Date, and link to most current Metrix Installation Manual. **Find it here:** with Metrix open, go to help, then License Stats. If Metrix does not open, (because the evaluation period has ended) the user is instead prompted by the License Status Box.
- f) **Max Release Date:** Free upgrades are included for 1 year from the date of the initial Metrix purchase. This date is coded into a License so it cannot unlock versions of Metrix that are released after this date. If it has been longer than a year OR if you are unsure of your Metrix Release Date, contact us through our request page:
<http://www.abraxasenergy.com/customer/lic/>
NOTE: Users are advised to compare their Max Release Date to the corresponding Version Release Date before downloading.
- g) **Evaluation Licenses:** Metrix is designed to auto-generate its own

Evaluation License with a 30 day duration for the initial installation OR if it detects that all previously installed versions have an older release date. **NOTE:** The Evaluation License permits full functionality of both Metrix and Report Maker, but you may only generate 5 reports at a time.


h) Expiration Date: this is displayed on the 6th line down in the License Status Box.

7. To request a full License:

a) Open the License Importer. Go to Microsoft Start Button > Programs > Metrix 4 > Import License.



- b) Clicking the request License button opens the License Request Form shown below. **Note:** your computer ID is already filled in.



The image shows a Windows-style dialog box titled "License Request by Email". It features a title bar with a gear icon and standard window controls (minimize, maximize, close). The dialog contains the following fields:

- User Name: [Empty text box]
- Company: [Empty text box]
- Phone: [Empty text box]
- Email: [Empty text box]
- Product: [Dropdown menu with "Metrix and Metrix Report Maker" selected]
- Computer ID: [Text box containing "256874537"]

At the bottom of the dialog are two buttons: "OK" and "Cancel".

- c) The License Request Form is configured to work with Microsoft Outlook Email. If you use another email server, right click anywhere in the frame of the form and the option to “Copy to Clipboard” will appear. Paste the form info into an email with any other pertinent info related to the nature of your request to helpdesk@abraxasenergy.com

8. To import a License

- a) Download the License file attachment from your email. Save (don't run or open) where you can find it. (The desktop is good for starters; it can be relocated after import) You can rename the License file as long as it retains the “.lic” extension.
- b) **NOTE:** Metrix will make its own copy after a successful import, but it is highly recommended that you save your won copy in a safe location where you keep important reference information.
- c) Open the License Importer. Go to Microsoft Start Button >

Programs > Metrix 4 > Import License (see above).

d) Click the “Import License” Button and browse to where you saved the License file.

e) **NOTE:** License details will appear in the left hand pane of the License Importer including computer ID, Max Release Date, Expiration Date, contact info, and more.

f) After successfully importing, click ok, and then close the License importer.

